


Brief Instruction



Software AJWin 3.6.4

© 12/2013 EN
iret GmbH
Paul Engelhard Weg 50a
D-48167 Münster



+49 .251 .61 51 38



+49.251 .61 76 31

E-Mail
Internet

info@iret.de

www.iret.de

iret

*Gesellschaft zur Entwicklung
elektronischer Steuerungen mbH*

1	Introduction.....	3
1.1	What is AJWin.....	3
1.2	The use of Existing Print Texts.....	3
1.3	AJWin Limitations.....	3
2	Installation.....	4
2.1	Installation of AJWin Software.....	4
2.1.1	The Selection of the Installation Directory.....	4
2.1.2	Installation of Codemeter Software.....	4
3	The First Startup.....	6
3.1	Notes for a Basic Configuration.....	6
3.1.1	Add a Printer.....	7
3.1.2	Immediately after Installation.....	7
3.1.3	From Main Window.....	7
3.2	Select and Edit Printers.....	7
3.3	Logon to the Software.....	9
4	Create and Edit Print Texts.....	10
4.1	Create a New Print Text.....	10
4.2	Insert, Move and Edit Objects.....	10
4.3	An alternative for Prompted Fields.....	11
5	Notes on Printout Configuration.....	12
5.1	Managing Configurations.....	12
5.2	Configuring Print Mode.....	12
5.3	Adjustment of the Encoder.....	12
5.4	Setting the Print Length.....	13
5.5	Setting Print Trigger.....	13
5.6	Setting Print Distance.....	14
6	Sending Print Texts to the Printer.....	16
6.1	General.....	16
6.2	Common Settings for Transmission.....	17
6.3	Copy Print Texts on a USB Flash Drive.....	17
7	Logos and Fonts.....	19
7.1	Logos on alphaJet C.....	19
7.2	Logos on alphaJet evo.....	19
7.3	Fonts.....	19
7.3.1	Installation of custom MFT fonts.....	19
7.3.2	Mapping of MFT fonts to TTF fonts.....	19

1 Introduction

1.1 What is AJWin

AJWin is a Windows software to create, manage and transfer print texts to an industrial continuous inkjet printer of type alphaJet-C, Evo, Into and others. Except the service functions the AJWin software can substitute nearly all functions of the printer terminal.

One of the main features of AJWin is that the print texts are independent of the actual printer: normally a print text can be used without changes for any printer of type alphaJet-C or Evo.

With additional modules the AJWin software can be connected with other IT- or production control systems of the customer.

1.2 The use of Existing Print Texts

Print texts that have been created directly on an alphaJet-C or Evo/Into printer can be used with AJWin after importing them into AJWin database.



Note!

The details of copying and importing of print texts is subject to chapter 6 of the user manual.

1.3 AJWin Limitations

The current version of AJWin has the following limitations:

1. There is no easy way to to make a complete printer backup/restore.
2. The current version of AJWin has no logo (symbol) editor included. Logos have to be prepared either with cGraphic software (mlg-format) from KBA Metronic or with an external software like paint (Windows bmp files).
3. It is not possible to use excel files as a database for complex print texts, although AJWin can use excel files as a source for single data fields.
4. For the alphaJet-Evo printer no service functions are provided.


2 Installation

2 Installation

2.1 Installation of AJWin Software

The installation is carried out similar to other standard Windows programs and for this reason only two things are pointed out here:

2.1.1 The Selection of the Installation Directory



i Note!

At this point you can select a directory on a network drive.

- This makes sense when different PC's shall work with the same print texts
 - The base installation is done on only one PC or server.
 - On all other PC's a desktop link to the ajwin executable file is sufficient.
-

2.1.2 Installation of Codemeter Software

i Note!

After base installation is done, the Codemeter software will be installed. Codemeter is a licensing software.

- AJWin can not be started before Codemeter installation has finished
-

**Note!**

After installation of Codemeter software AJWin can be used for a period of 30 days (evaluation licence).

3 The First Startup

3 The First Startup


When first starting AJWin a number of dialog boxes with the most important settings for your PC will appear (in this case the PC is referred to as a “station”).



Confirm with „OK“.

3.1 Notes for a Basic Configuration

In this dialog some basic properties of AJWin are configured. When you first start AJWin you should only configure the „Main window“ and the „Language“. All other settings can be adjusted later (see user manual chapter 5.4)




Main window option	description
Single print job	This is the default value! The main window shows exactly one print text. Typical application: <ul style="list-style-type: none">• The PC is always connected to the printers.• The operator selects the current print text at the PC:• The display of the printer is only used for maintenance.
Item list processing	The main window contains a list with several different print texts. Typical application: <ul style="list-style-type: none">• Several print texts have to be sent at the same time. They are stored permanently in the printer.• The operator selects the actual print text at the display of the printer.
Multiple printhead application	The main window shows two or three print texts for every article number.

Main window option	description
	Typical application: <ul style="list-style-type: none"> • Pharmaceutical industry where one box needs multiple printouts
Customer application	Must not be used without explicit permission from a service technician.

3.1.1 Add a Printer

3.1.2 Immediately after Installation




You see this dialog at the initial configuration of a station. When you confirm with „Yes“ a list of predefined printers is shown, see also chapter 3.2.

3.1.3 From Main Window

The list of printers configured for use at this PC is shown at the left side of the main window.

To add a new printer open the context menu of the station (right mouse button) and select „add printer“ to show you a list of all printers available (see chapter 3.2).




3.2 Select and Edit Printers

After the selection of a printer (picture 1) you can change the communication parameters with the button „edit“ (picture 2).


For a detailed description see chapter 5.2 in the user manual.

3

The First Startup



With the buttons „new“ and „edit“ you get the printer settings. After selection of the printer type (tab „Base settings“) you have to configure the communication.



**Note!**

When configuration is finished, both dialogs must be closed with „OK“, to see the printer in the main window.

3.3 Logon to the Software

For the first login you should type

- User name: Admin
- Password: didu

4 Create and Edit Print Texts

4 Create and Edit Print Texts

4.1 Create a New Print Text

If you want to make a new print text you must create one first:

- In the “Item list” main window use the buttons on the right side of the main window (see user manual chapter 3.11).
- In the “Single Print Job” or “multiple printhead application” main windows you can create a new print text either by using the menu “Print Texts” or through the “Product Overview” (also see user manual chapter 7.6.1)

After you created the print text you can edit it.


4.2 Insert, Move and Edit Objects

At the bottom of the program window there is a white area which is used to display the print text.



The print text is a selection of various objects (text, logo (symbol), barcode and others):

- By clicking the right mouse button, you open a menu that is used to create new objects. Before selecting a menu item the according dialog box will appear (see user manual chapter 4.2.1).



- An existing object can be changed by double clicking the object.
- When you want to move an existing object, click and hold the left mouse button over the object and then move it to a new position.
- Objects can be moved pixel by pixel using the arrow keys. (Left click to select then move)
- Multiple objects can be moved or deleted simultaneously. To mark multiple objects, click on each object while holding the CTRL-key pressed.

To edit a print text a new dialog box will appear, that means no print texts can be edited directly in the print text display area.




Please note

- A print text should always start at the bottom edge to ensure that maximum printing speed can be achieved.
- In order to freely place objects you must deactivate the “Auto arrange” option. If necessary you may also need to select a smaller grid size then 8. (see also chapter 7.4 in the user manual)

4.3 An alternative for Prompted Fields

In AJWin these fields are named „variable fields“, they have extended capabilities. In contrast to the alphajet the variable fields have to be declared before using them.



Note!

Variable fields are described in detail in the user manual.

5 Notes on Printout Configuration

5 Notes on Printout Configuration

5.1 Managing Configurations

Every print text has some additional settings associated. These settings are called the configuration, and they affect various aspects of the printout, e.g. density of strokes, orientation and maximum printing speed.

Managing configurations with AJWin differs from what alphajet-C and Evo users may expect:

- Every print text has its own configuration
- The selected print mode is part of the configuration
- The configuration values are widely independent from the printer model
- Settings concerning adjustment (shaft encoder) and product sensor are stored with the printer and not together with the configuration
- The expected length of the printout is stored with every print text

Some details of this concept are explained in the following sections.


5.2 Configuring Print Mode

The print mode is stored with every print text and is a result of „print height“ and „print quality“. The native print mode is determined not before sending the print text to the printer.

Example: print height „7 Pixel“, „high quality“


→ results in print mode „1g“ for the alphajet-C

→ and for Evo in PM_B15 or PM_15“ (depending on model)




5.3 Adjustment of the Encoder

The encoder settings are stored with the printer parameters. The given values are the base for calculating the length of the printout.



5.4 Setting the Print Length

For every print text the expected length is set in the main window:



Besides the desired length you see the actual length which depends on the type of printer and its encoder values.



Technical note

Internally AJWin only uses the distance between two strokes instead of the total length of the printout. Thus the print length is automatically adjusted when the print text changes.

The resulting distance between two strokes is shown in the configuration:




5.5 Setting Print Trigger


How the print is triggered is determined at two different places: „printer settings - print trigger“ and „configuration - print trigger“.

5 Notes on Printout Configuration

- In the printer settings you select if a product sensor is installed or not



- In the configuration you select for every print text if autorepeat is on or off.



Mode AJC / Evo	AJWin: printer settings	AJWin: configuration
continuous	Start key	autorepeat on
repetition	sensor active high / low	autorepeat on
start key	Sstart key	autorepeat off
product sensor	sensor active high / low	autorepeat off

5.6 Setting Print Distance


In AJWin there are two parameters for the print distance:

- The distance between product sensor and printer: this value is given by the mechanical installation of printhead and product sensor.
- The position of the printout on the product: this value is given by the customers request where the print is placed on the product.

When sending the print text to the printer these two values are added together and stored in the parameter „print distance“ of the alphaJet.

Using two values instead on one has the following advantages:

- When mechanical installation changes, the first value must be set only once and not for every product.
- The print text can be used without changes on different production lines.




6 Sending Print Texts to the Printer

6 Sending Print Texts to the Printer

6.1 General

To send a text first select the printer and then click on the button „Send“. Before the transmission starts you will be prompted for the actual content of all variable fields used in the print text.



After transmission has finished the following data should appear on the printer:

1. A new print text
2. A configuration with the same name as the print text
3. For alphajet-C you find transmitted logos on the ram disk (see chapter 7.1)




Take care!

Sending a print text will interrupt a running printout

- This can result in wrong printouts
- Be sure the printer is not in use while sending print texts

6.2 Common Settings for Transmission

Many customers have their own ideas how the print texts are named on the printer, therefore you can choose between some variants in the station settings.




Typical settings are:

- Create automatically: the names are consecutively numbers (0000, 0001...)
- Item number: the same name as in AJWin

6.3 Copy Print Texts on an USB Flash Drive

Since AJWin version 3.6.4 you can save print texts for an Evo printer in an directory of choice (e.g. an USB drive). You do this in the same way as if you send the text to the printer, but you the communication interface has to be of type „FILE“.



At transmission two subfolders are created in the data directory:

6

Sending Print Texts to the Printer

- in the subfolder „Label“ all print texts are stored
- in the subfolder „Config“ the configurations are stored



Tip

The data directory can be located on a hard disk drive but may also be:

- an USB Flash Drive
 - an UNC path to a location on a network drive (i.e. [\\printer1\user](#))
-

7 Logos and Fonts

7.1 Logos on alphaJet C

When transmitting a print text AJWin will copy all logos for this print text to the ramdisk of the printer. The ramdisk is used because the number of write accesses on the flash drive is limited.

Normally the logo files are consecutively numbered and have not the same names as on the PC.



Take care!

After restarting the printer the print text has to be send again, because any logo file on the ram disk is lost during restart.

7.2 Logos on alphaJet evo

At transmission to alphajet-Evo a logo is not stored as a separate file on flash- or ramdisk but it is directly embedded into the print text.

7.3 Fonts

AJWin exclusively uses fonts in metronic alphajet-C format (MFT format), the TTF fonts of the evo are not supported natively. This has the following consequences:

- On the screen of your PC you see the alphajet-C font.
- You can not simply copy a TTF font to the printer and use it on the PC, because the font also has to be present on the PC as an MFT-font.



Note!

A print text with an unknown font is displayed as a blue rectangle in AJWin.

7.3.1 Installation of custom MFT fonts

For the representation in AJWin you only have to copy the font to the directory „ajwin\font“ and restart AJWin. You can transmit the font to the printer with the function „Extras“ - „Copy files“ - „Copy fonts to printer“.

7.3.2 Mapping of MFT fonts to TTF fonts

Normally you can use all standard fonts that are present in MFT format, because KBA Metronic provides TTF fonts with the same name. For technical reasons there are some exceptions to this rule and AJWin maintains a translation table:

AJC-Font	Evo-Font	
A15x12	A15x11	
A23x15	A24x15	